



Installation and Administration Guide

rasdaman version 8.0

rasdaman Version 8.0 Installation and Administration Guide. Last updated on 31 October 2010.

Rasdaman Community is free software: you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation, either version 3 of the License, or (at your option) any later version.

Rasdaman Community is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with rasdaman. If not, see www.gnu.org/licenses. For more information please see www.rasdaman.org or contact Peter Baumann via baumann@rasdaman.com.

Copyright 2003, 2004, 2005, 2006, 2007, 2008, 2009 Peter Baumann / rasdaman GmbH.

All trade names referenced are service mark, trademark, or registered trademark of the respective manufacturer.

Preface

Overview

This guide provides information about how to use the rasdaman multidimensional database system, in particular: installation and system administration.

rasdaman interoperates with conventional database systems, be they relational or object-oriented, in an integrated manner. There is a clear, natural distribution of work between the two different database systems according to the data types: multidimensional data are managed by rasdaman, whereas the alphanumeric data remain in the conventional system¹. At the bottom line, however, all data - multidimensional or

¹ In some disciplines, multidimensional data are referred to as *raw data* or *processed data*, depending on their status, whereas the accompanying alphanumeric data are called *meta data*.

alphanumeric - end up in the same physical database, thereby considerably easing database maintenance wrt. consistency, backup, etc. To this end, rasdaman makes use of the storage management facilities of the database system it is coupled to.

For the purpose of this documentation, we will call the conventional database system to which rasdaman is interfaced the *base DBMS*, understanding that this base DBMS is in charge of all alphanumeric data maintained as relational tables or object-oriented semantic nets.

rasdaman is available on different base DBMSs. This manual covers the base DBMS independent issues. Please consult additionally the *External Products Integration Guide* available for the different base DBMSs, as well as the other rasdaman guides for features of the rasdaman system which are common to all platforms.

Audience

The information in this manual is intended primarily for database and system administrators.

Rasdaman Documentation Set

This manual should be read in conjunction with the complete rasdaman documentation set which this guide is part of. The documentation set in its completeness covers all important information needed to work with the rasdaman system, such as programming and query access to databases, guidance to utilities such as the graphical-interactive query tool *rView*, and release notes.

In particular, current restrictions, known bugs, and workarounds are listed in the Release Notes. All documents, therefore, always have to be considered in conjunction with the Release Notes.

The rasdaman Documentation Set consists of the following documents:

- C++ Developer's Guide
- Java Developer's Guide
- Query Language Guide
- Installation and Administration Guide
- PostgreSQL Integration Guide
- Error Messages
- rView Guide
- Release Notes

Table of Contents

1 Getting Started	7
1.1 System requirements	7
1.2 Server Types	8
1.3 Support	8
2 Getting It Up: System Installation and Database Creation	9
2.1 Hardware Requirements	9
2.2 Software Requirements	10
2.3 Download and Install rasdaman File Set	10
2.4 Establish Dedicated Operating System User	11
2.5 Base DBMS Set-Up	11
2.6 Database Initialization	12
2.7 Server Configuration (optional)	12

2.8 Server Start	12
2.9 Demo Database	13
3 rasdaman Architecture.....	14
3.1 Executables Overview	14
3.2 Server Manager and Server	15
4 Server Administration	19
4.1 General Procedure.....	19
4.2 Running the Manager	20
4.3 <code>rascontrol</code> Invocation	21
4.4 <code>rascontrol</code> Command List	24
4.5 Server Hosts.....	24
4.6 rasdaman Servers.....	25
4.7 Database Hosts.....	27
4.8 Databases	28
4.9 Server Start-up and Shutdown	29
4.10 Inter-Manager Status Request	30
4.11 Users and Their Rights	30
4.12 Server Control Options	32
4.13 Miscellaneous.....	33
5 Database User Password Administration	34
6 Example Database and Programs	36
6.1 Example Database.....	36
6.2 Example Programs.....	37
7 Troubleshooting	39
7.1 Cannot start rasdaman server	39

1 Getting Started

This section outlines the hardware and software requirements and describes the rasdaman distribution directory. Make sure you are familiar with this before proceeding to the next section which describes the installation procedure.

1.1 System requirements

For successful operation of rasdaman, the hardware and software environment needs to comply with the following server and client side requirements.

Hardware

It is recommended to have at least 3 GHz processor frequency and 8 GB main memory.

Disk space depends on the size of the databases, as well as the requirements of the base DBMS of rasdaman chosen. The footprint of the rasdaman installation itself is around 400 MB.

Software

Server-side software requirements are:

- One of the operating systems supported.
- Adobe Acrobat Reader for reading the manuals (available from <http://www.adobe.com/products/acrobat/readstep2.html>), as well as some Web browser capable of HTML 4.0.
- One of the relational database systems supported by rasdaman, configured for operation with rasdaman (cf. *rasdaman External Product Guides*).
- If you intend to use Java: Java Runtime Environment (JRE) 1.6 or higher (available from <http://www.sun.com>)
- The following packages: git-core, g++, autoconf, libtool, gawk, bison, postgresql, libecpg-dev, sun-java6-jdk, libncurses5-dev, libhdf4g-dev, flex, libpng12-dev, libjpeg-dev, libnetpbm10-dev, libreadline-dev, libtiff-dev, make.

The configuration script (see Section 2.2) checks for missing components.

1.2 Server Types

Historically, rasdaman internally uses three different client/server communication protocols: `RPC`, `HTTP`, and `RNP`. The `RPC` and `HTTP` types are deprecated, and `RNP` is default and recommended (exception: `rview`, which still requires `RPC`).

- `SUN RPC`. This mechanism is deprecated. Only `rview` still needs an `RPC` type server running.
- `HTTP`. This has been used by rasdaman applications programmed in Java, such as `rasogc`. It is deprecated.
- `RNP`. This protocol substitutes both the other protocols. It is the default for all tools except `rview`.

To accommodate the different clients, an appropriate server has to be started as the counterpart. For example, a Java application needs an `RNP` or `HTTP` type server and is not able to communicate with an `RPC` type server.

The communication type of a rasdaman server is set via `rascontrol` (see Section 4.6).

1.3 Support

For support in installing rasdaman and any other question you may contact rasdaman GmbH at www.rasdaman.com.

2 Getting It Up: System Installation and Database Creation

This section describes how to install rasdaman, software package dependencies, and how to initialise rasdaman and the base DBMS so that the rasdaman system finally is up and running.

Please read this in conjunction with the rasdaman *External Product Integration Guide* for your particular base DBMS brand and the relevant manuals of the base DBMS vendor.

This section outlines the procedure for installing rasdaman from scratch. For incremental installation, such as from patch files and updates or upgrades follow the particular instructions there (e.g., in the release notes).

2.1 Hardware Requirements

Make sure that the target machine complies with the hardware requirements listed in Section 1.1.

2.2 Software Requirements

You need to download and install the following packages which are required by rasdaman:

- **tools:** git-core, make, autoconf, automake, libtool, gawk, flex, bison, ant, gcc-c++, libstdc++, sun-java6-jdk, Tomcat (or another suitable servlet container)
- **general libraries:** libreadline-dev, libopenssl-devel, libncurses5-dev
- **database:** PostgreSQL 8.x, libecpg-dev
- **image formats:** libtiff-dev, libjpeg-dev, libhdf4g-dev, libpng12-dev, libnetpbm10-dev

Warning

Do **not** use versions PG 8.3.0 to 8.3.6 inclusive, it **won't work**.

2.3 Download and Install rasdaman File Set

Create Dedicated User

While rasdaman can be installed and run under any operating system user, for security reasons it is strongly recommended to create a dedicated user to shield rasdaman activity from the rest of the system.

Download

You can get a complete *rasdaman Community* file set from www.rasdaman.org.

After download, execute the following steps:

```
tar xvfz rasdaman-<version>.tgz
```

This creates a directory `rasdaman-<version>`.

Installation

Step 1: The following command will prepare compilation for your system.

```
./configure
```

Any missing components will be reported. For customization there is a set of options available, see the `--help` option. In particular, to change the default installation directory, `/usr/local`, use option `--prefix`.

Example for an alternative location:

```
./configure --prefix=/usr/local/rasdaman-8.0.0
```

Example: To install locally under user `~rasdaman` the invocation can be formulated as:

```
./configure --prefix=~rasdaman
```

Step 2: Next, compile and link rasdaman:

```
make
```

Step 3: Finally, install them at the place specified before.

```
make install
```

If the target location is not writable by the current user (such as system directories) then the above command needs to be run as superuser.

Step 4: Finally, to use the rasdaman executables conveniently, add the path definitions to the script of that login under which the rasdaman server will run.

Example: Depending on the operating system flavour, installation, and preferences, the following line can be put, e.g., into file `~rasdaman/.bash_profile`:

```
export PATH=$RASDAMAN/bin:$PATH
```

In the remainder of this document the installation path is referred to as `$RASDAMAN`.

2.4 Establish Dedicated Operating System User

For security reasons it is recommended to create a dedicated operating system user account under which rasdaman will be operated (such as `rasdaman`). In the sequel it is assumed that this user account has been created and that you are logged in as user `rasdaman`, e.g., by using this command:

```
su - rasdaman
```

Note

It is no problem to run rasdaman under any other user; in this case, adjust the commands listed in the sequel where necessary.

2.5 Base DBMS Set-Up

Create Relational Database

The base DBMS has to be set up according to the instruction in the *rasdaman External Products Integration Guide*. In particular it is strongly recommended to study Section *Database Creation Procedure* in said document because it may be necessary to execute base DBMS specific steps before actually creating a database.

For example, for PostgreSQL a database instance needs to be created under the same operating system user under which rasdaman will be operated (such as `rasdaman` as recommended above). The following commands create a PostgreSQL database sitting in directory `$DATADIR` and with owner `rasdaman`:

```
initdb -D $DATADIR  
pg_ctl -D $DATADIR start
```

Verify database

Roughly speaking, base DBMS configuration is ok if the SQL interpreter can successfully connect to the base DBMS when logged in to the target user account, in the above discussion: `rasdaman`. If this does not work then you may have to reconsider `$PATH` and `$LD_LIBRARY_PATH` settings.

2.6 Database Initialization

Create rasdaman database

The `create_db.sh` script creates and initializes a rasdaman database named `RASBASE` by instantiating a set of MDD types. It has no parameters and is invoked as:

```
create_db.sh
```

Notes

For creation of new databases, rasdaman servers have to be restarted, otherwise the databases may not be recognized. Updating a rasdaman database schema (that is: creating new types and the like), however, does not need a server restart.

Some base DBMSs support the notion of multiple databases. In these cases, rasdaman also supports multiple databases.

2.7 Server Configuration (optional)

Rasdaman is a multi-server multi-user system. The server processes available must be configured initially, which is done in file `$RASDAMAN/etc/rasmgr.conf`. For distribution, this configuration contains only one server process going by a name like, for example, `N1`. If this is fine then you can just leave it as it is. If you want to change this by modifying server startup parameters or increasing the number of server processes available then see Section 4 for details on how to do this; probably you want to change this only once the initial, single-server installation has been verified to be operational.

2.8 Server Start

Start rasdaman by calling `start_rasdaman.sh`.

Notes

- Messages printed by `start_rasdaman.sh` will not always show the detailed system state. If, for example, the rasdaman servers fail to contact the base DBMS then nevertheless a message “Server started” may appear.

Workaround: use this to get the actual server state, as user `rasdaman`:

```
rascontrol -e -x "list srv"
```

2.9 Demo Database

The rasdaman distribution contains a demo database which serves as a first test of successful installation.

Inserting demo data into the fresh database is done through

```
insertdemo.sh localhost 7001 \  
  $RASDAMAN/share/rasdaman/images rasadmin rasadmin
```

Note that repeated invocations are not harmful – each of the sample collection will simply receive additional objects made of the same images.

After successful completion, you can check whether the three rasdaman collections containing the example images have been created through:

```
rasql -q "select r from RAS_COLLECTIONNAMES as r" \  
  --out string
```

This command shows a list of all collections existing in the database. There should be `mr`, `mr2`, and `rgb`.

Further, you can inspect these data using, for example, `rview` (see the *rasdaman rView Guide*).

Congratulations! At this point, if everything completed successfully, rasdaman is up and running and prepared for data definition, data import and retrieval, and any other suitable task.

3 rasdaman Architecture

The parallel server architecture of rasdaman offers a scalable, distributed environment to efficiently process even very large numbers of concurrent client requests. Yet, server administration is easy to accomplish, with only few things to do to have a smoothly running, highly performant installation. Moreover, the system is implemented in a special high availability technique where most server management operations can be done with the server up and running, limiting the need for a server shutdown to the absolute minimum.

In this Section the general rasdaman server architecture is outlined. It is recommended to study this section so as to understand server administration terminology used in the next Section.

3.1 Executables Overview

The following executables are provided in the `bin/` directory, among others:

- `rasmgr` is the central rasdaman request dispatcher;

- `rasserver` is the rasdaman server engine, it should not (and actually cannot) be invoked in a standalone manner;
- `rascontrol` allows to interactively control the rasdaman server by communicating with `rasmgr`;
- `raspasswd` allows to administrate rasdaman database user logins;
- `rasdl` is the command-line based schema maintenance tool; this is (currently) not a client application, but connects directly to the relational database manager.
- `rasql` is the command-line based query tool.

The `rasdl` and `rasql` tools are explained in detail in the *rasdaman Query Language Guide*.

3.2 Server Manager and Server

Overview and Terminology

The rasdaman server configuration consists of one dispatcher process per computer, `rasmgr` (we will refer to it as *manager* in the sequel), and server processes, `rasserver` (referred to as *servers*), of which at a given time none, one, or several ones can be running. All server processes are under control of the manager. Server manager and rasdaman server(s) all run on the same physical hardware, the *rasdaman host*.

The servers resolve requests, thereby generating calls to the relational database system which in turn accesses its database files. For the purpose of this manual, the relational server together with the database it maintains are collectively called the *database*. The machine the relational database server runs on is referred to as *database host* (Figure 2).




Figure 2: Overall server hierarchy, introducing the terminology for rasdaman hardware and software environment

Server Structure in General

The manager accepts client requests and assigns server instances to them, taking them from the pool of server processes it maintains. In

distributed installations, it keeps contact to the managers on other machines to further dispatch client requests across all the rasdaman servers available. Whenever needed, the administrator can launch further server instances, or shut them down again.

Upon system configuration definition (see Section 4), a unique name is assigned to each server identifying it to the manager.

Each rasdaman server is assigned to a relational database server, laid down in the manager configuration file. Databases can be registered and associated to particular rasdaman servers at any time.

rasdaman hosts and database hosts are identified by their resp. host name in common domain address form, e.g., `martini.rasdaman.com` or `199.198.197.50`.

`Rascontrol` is the interactive front-end to `rasmgr` and, as such, the main utility for user and system management. It provides the necessary functions to manage the whole system configuration, to add and remove user, to change their rights, and to obtain information about system activity.

The rasdaman server, i.e., `rasserver`, is controlled by the manager which starts and stops server instances. Hence, the `rasserver` executable should not (and actually cannot) be invoked directly.

Dynamic Server Assignment

The process of client/server communication and server scheduling is done as follows (see numbers in Figure 3).

1. The client starts every `OPENDB` and `BEGIN TRANSACTION` request with an HTTP call to the manager, providing the required service type (RPC, HTTP, etc.) and the database name, together with user name and password.
2. The manager's answer is the server ID of a free server, or an error message in case no server is available or access is denied for the given login.
3. Client-Server communication to perform the database requests.
4. Upon `CLOSEDB` and `ABORT/COMMIT TRANSACTION` the server informs the manager that it is available again. This is also done upon a client timeout.

These negotiation steps are performed between client library and server, hence transparent to the application.

The rasdaman server system is started by invoking the server manager `rasmgr` (see Section 4.2). If it finds a configuration file, then automatically all servers indicated will be started; alternatively, server configuration can be done directly through `rascontrol` (see Section 4.3).




Figure 3: Internal server management

System Start-up

Invocation of the `rasmgr` executable must be done under the operating system login under which the rasdaman installation has been done, usually (and recommended) `rasdaman`.

Cascaded Servers

rasdaman servers running on different computers can be coupled so as to form one single server network. To this end, one of the rasdaman managers is assigned to act as master, doing the overall management, and all the others are slave rasdaman managers, doing local server management as before.

Clients address only the master manager, hence from a client point of view nothing changes, there still is only one point of service.

On every machine hosting rasdaman servers a separate manager has to run. The manager maintains a configuration and an authorization file. None of them should be changed by the administrator, as they are generated, maintained, and overwritten by the manager.

4 Server Administration

In this Section, it is explained how the manager is used to start up and shut down servers, as well as how to monitor and influence server state.

It is recommended to first study the previous section so as to understand server administration terminology used here.

4.1 General Procedure

rasmgr VS. rascontrol

It is important to distinguish between the manager, `rasmgr`, and its control front-end, `rascontrol`. The manager runs as a background process, supervising activity of local (and possibly remote) rasdaman servers. Interaction between user (i.e., administrator) and the manager takes place through the interactive control front end.

In the sequel, it is first described how to launch the manager `rasmgr`, then `rascontrol` commands are detailed.

Important Security Note

To remain compatible with older rasdaman versions, clients use login “rasquest” / password “rasquest” by default (i.e., when no user and password are explicitly set by the application). In the distribution configuration, this user is defined to have read-only access to the databases – in plain words,

- According to the default configuration,
- users can access,
- but not manipulate databases
- without authentication.

Therefore, the administrator is strongly urged to adapt authentication settings to the local security policy before switching databases online.

See Section 4.11 to learn more about user management mechanisms.

4.2 Running the Manager

Manager Startup

Starting up the rasdaman system is done by invoking the rasdaman manager, `rasmgr`, from a shell under the `rasdaman` operating system login. Usually the manager will be sent to the background:

```
rasmgr &
```

Starting `rasmgr` is the only direct action to be done on it. Any further administration is performed using `rascontrol`.

Note that, unless a server configuration has been defined already, no rasdaman server is available just by starting the manager.

Master vs. Slave

Invocation of a master and slave manager is different. A master manager is the central server access turnpike accepting requests from clients; hence, the only additional information it needs is the port to listen to.

A slave manager, on the contrary, is a relay station which maintains local rasdaman servers and keeps contact to the master manager. Hence, a slave manager additionally must be provided with domain name and port number of the master manager to which the slave is subordinate. Below is the syntax for the two variants.

Invocation Synopsis

Master manager invocation synopsis:

```
rasmgr [--help] [--hostname h] [--port p]
      --help      print this help
```

```

--hostname h host on which the manager process is running is
                accessible under name / IP address h
                (default: output of Unix command hostname)

--port p       manager will listen to port number p
                (default: 7001)
    
```

Slave manager invocation synopsis:

```

rasmgr [--help] [--name h] [--port p] --master m [--mport x]

--help          print this help

--name h      master manager will know this slave started as
                running on host with name h
                (default: host name of machine)

--port p     manager will listen to port number p
                (default: 7001)

--master m   assume m as domain name of the master manager
                (no default, mandatory parameter)

--mport p   assume p as port number of the master manager
                (default: 7001)
    
```

Syntactically, the distinction between launching a master and a slave manager is in the `--master m` option: if this option is missing, then a master server manager is started; if it is present, a slave is started which will try to connect to master *m*.

The normal launch procedure is to start the master first, then every slave, providing the master's host name and port number. The slaves try to contact the master and to register their status. If the master is not up, or cannot be contacted, the slave also waits to be contacted. The only reasons why a slave stops working at start-up time is when it gets a refusal by the master; which happens when the master doesn't know the slave.

Examples

To start a master manager which will listen at port 7001:

```
rasmgr --port 7001
```

To start a slave manager on server `martini` (also listening on port 7001) which will be subordinate to the master manager on host `campari` (both machines are assumed to run in the same local networks domain):

```
rasmgr --name martini --port 7001 \
      --master campari --mport 7001
```

4.3 *rascontrol* Invocation

The manager front end, `rascontrol`, is a command-line interface used for rasdaman administration. It allows to define the whole rasdaman

system configuration, including start up and shut down of server instances and user logins and rights.

To secure access to the server administration facilities, `rascontrol` performs a login process requesting login name and password similar to the Unix `rlogin` command. User name must be one of the users defined in the rasdaman authentication list (see Section 4.11).

rascontrol Synopsis

```

rascontrol [-h|--help] [--host h] [--port n] [--prompt n]
           [--quiet]
           [--login|--interactive|--execute cmd|--testlogin]

--host h      name of the host where the master manager runs
              (default: localhost)

-h
--help       this help

--port n      port number at which the master manager listens to
              requests
              (default: 7001)

--prompt n    change rascontrol prompt as following:
              0 - prompt '>'
              1 - prompt 'rasc>'
              2 - prompt 'user:host>'
              (default: 2)

--quiet       quiet, don't print header
              (default for --login and --testlogin)

--login       print login and password, obtained from
              interactive input, to stdout, then exit
              (see Script Use below)

--interactive read login and password from environment variable
              RASLOGIN instead of requesting it interactively

--execute cmd execute single cmd and exit (batch mode);
              all text following -x until end of line is passed as
              command; this option implicitly assumes -e

--testlogin   just do a login and nothing else to check whether
              the login/password combination provided in the
              RASLOGIN variable is valid
    
```

Interactive Use

In interactive use, `rascontrol` will be invoked with the host parameter only. Following successful authentication, `rascontrol` accepts command line input from `stdin`.

Here is an example session (`mypassword` will not be echoed on screen):

```

tcsh> rascontrol
Login name: mylogin
Password: mypasswd
mylogin:localhost> define dbh h1 -connect /
mylogin:localhost> define db d1 -dbh h1
mylogin:localhost> define srv s1 -host localhost
                        -type h -dbh h1
mylogin:localhost> up srv s1
mylogin:localhost> save
mylogin:localhost> exit
tcsh>

```

Script Use

Alternatively to interactive login, user and password information can be taken from the environment variable `RASLOGIN`. This variant is suitable for batch scripting in conjunction with the `-x` option.

The following example shows how first the `RASLOGIN` is set appropriately:

```
export RASLOGIN=`rascontrol --login`
```

...and then a sample Unix shell script which starts all rasdaman servers defined in the system configuration, performing implicit login from the environment variable contents which has been obtained from the previous command and pasted into the shell script:

```

#!/bin/ksh
export RASLOGIN=rasadmin:mytotallyencryptedpassword
rascontrol -x up srv -all

```

Comments in Scripts

To enhance legibility of scripts, `rascontrol` accepts comments in the usual shell syntax: Lines beginning with a hash sign `#` will be ignored, whatever they may contain. An example is usage in shell *here documents* (type `man sh` in your favourite shell for further information on this feature):

```

rascontrol <<EOF
# this is the command submitted to rascontrol:
list srv -all
# now terminate rascontrol:
exit
# the following line terminates rascontrol input:
EOF

```

Prefabricated Script

To ease system installation, a shell script, `rasconfig.sh`, is delivered in the `bin` directory which contains initial server definitions to set up a rasdaman Classic Edition configuration (i.e., one server process).

Don't simply run this script as is; prior to running it you may want to first understand it and then adapt it to your local situation.

4.4 *rascontrol* Command List

Command Synopsis

help	display information (general or about specific command)
exit	exit <i>rascontrol</i>
list	list info about the current status of the system
up	start server(s)
down	stop server(s) and <i>rasdaman</i> server manager(s)
define	define a new object
remove	remove an object
change	change parameters of objects
save	make configuration changes permanent
check	check current status of a slave <i>rasdaman</i> server manager

In the remainder of this section, commands are explained in detail.

4.5 Server Hosts

Define Server Hosts

```
define host h -net n -port p
    h          symbolic host name
    -net n     set network host name to n
    -port p    TCP/IP port on which the rasdaman manager will
                listen
```

Change Server Host Settings

```
change host h [-name n] [-net x] [-port p]
              [-uselocalhost [on|off] ]
    h          host name whose entry is to be updated
    -name n   change host name to n
    -net x    change network name to x
    -port p   change port number to p
    -uselocalhost [on|off]
                use domain name localhost (IP address 127.0.0.1)
                instead of regular network host name; usually this
                speeds up communication a little
                (master server manager only; default: on)
```


Note that it is not possible to change network name or port for a host while this server is running.

Remove Server Host Definitions

```
remove host h
```

h host name whose entry is to be deleted

Remove host *h* from the definition table.

It is not possible to remove a host definition while the corresponding host has active servers.

Status Information

```
list host
```

List all hosts currently defined.

4.6 rasdaman Servers

Define rasdaman Servers

```
define srv s -host h -type t -port p -dbh d  
[-autorestart [on|off] [-countdown c]  
[-xp options]
```

s a unique, not yet used name for the server

-host *h* name of the host where the server will run

-type *t* communication type: *t* is *r* for RPC, *h* for http

-port *p* the RPC *program number* for RPC servers (recommended: 0x2999001 - 0x2999999), TCP/IP port for http servers (recommended 7002 - 7999)

-dbh *d* database host where the relational database server to which the rasdaman server connects will run

-autorestart *a*
for *a=on*: automatically restart rasdaman server after unanticipated termination
for *a=off*: don't restart
(default: *a=on*)

-countdown *c*
for *c>0*: restart rasdaman server after *c* requests
for *c=0*: run rasdaman server indefinitely
(default: *c=1000*)

-xp *options* pass option string *options* to server upon start
(default: no options, i.e., empty string)

Option `-xp` must be the last option. Everything following “`-xp`” until end of line is considered to be “`options`” and will be passed, at startup time, to the server; see *Server Control Options* below for the list of options available.

Change Server Settings

```
change srv s [-name n] -type t [-port p] [-dbh d]
           [-autorestart [on|off]] [-countdown c]
           [-xp options]
```

`s` change settings for server `s`

`-name n` change server name to `n`

`-port p` change port number to `p`

`-dbh d` new database host where the relational database server runs to which the rasdaman server connects

`-autorestart a`
for `a=on`: automatically restart rasdaman server after unanticipated termination
for `a=off`: don't restart

`-countdown c`
for `c>0`: restart rasdaman server after `c` requests
for `c=0`: run rasdaman server indefinitely

`-xp options` pass option string `options` to server upon start

Option `-xp` must be the last option. Everything following “`-xp`” until end of line is considered to be “`options`” and will be passed, at startup time, to the server; see *Server Control Options* below for the list of options available.

Restrictions:

- The server host cannot be changed.
- The server name cannot be changed while the server is up.
- The new settings will be used only next time the server starts.

Remove rasdaman Server Definitions

```
remove srv s
           h server name whose entry is to be deleted
```

Remove server `s` from the definition table.

It is not possible to remove a server definition while the corresponding server is up and running

Status Information

```
list srv [ s | -host h | -all ] [-p]
           s give information about server s
```

- `-host h` give information about all servers running on host *h* information is requested
- `-all` list information about all servers on all hosts (default)
- `-p` additionally list configuration information

The first variant prints status information of the currently defined server(s); if *s* is provided, then only server *s* is listed.

4.7 Database Hosts

Define Database Hosts

```
define dbh h [-connect c]
```

- h* a unique symbolic database host name, usually the host machine name
- `-connect c` the connection string used to connect the `rasserver` to the database server, i.e., the `-connect` parameter for `rasserver`

Change Database Host Settings

```
change dbh h [-name n] [-connect c]
```

- h* database host whose entry is to be changed
- `-name n` change symbolic database host name to *n*
- `-connect c` change connect string to *c*

The connection string can be changed at any time, however the servers will get the information only when they are restarted.

Remove Database Host Definitions

```
remove dbh h
```

- h* database host name whose entry is to be deleted

Remove database host *h* from the definition table.

It is not possible to remove a database host definition while this database host has active servers connected to it.

Status Information

```
list dbh
```

List all relational database hosts currently defined.

4.8 Databases

Databases represent the physical database itself, together with the relational database server accessing them. It is possible to have multiple database definitions in the rasdaman server environment which are distinguished by the database host; the interpretation, then, is that the same contents (be it the same physical database or a mirrored copy) is available through relational servers running on the different hosts mentioned. In other words, when a client opens a database, the server manager can freely choose any of the database hosts on which the database indicated is defined.

The pair (database,database host) must be unique.

Define Databases

```
define db d -dbh db
    d                define database with name d
    -dbh db        set database host name to db
```

Change Database Settings

```
change db d -name n
    d                database whose name is to be changed
    -name n        change to new database name n
```

Remove Database Definitions

```
remove db d -dbh db
    d                name of database to be removed
    -dbh db        host name of database to be removed
```

Remove definition of database *d* from the definition table. The database itself remains unchanged, it is not physically deleted.

It is not possible to remove a database definition while the corresponding database has open transactions.

Status Information

```
list db [ d | -dbh h | -all ]
    d                give information about servers connected to
                    database d
    -dbh h          give information about all servers connected to
                    database d via database host h
    -all             list information about all servers connected to any
                    known database (default)
```

List relational database(s) defined.

4.9 Server Start-up and Shutdown

Server Start

```
up srv [ s | -host h | -all ]
    s                start only server s
    -host s          start all servers on host h; this requires that a
                    manager has been started on this host previously.
    -all             start all servers defined; note that only those
                    servers can be started on whose host a manager is
                    currently running.
```

Look up the named server(s) in the definition list, and start the specified one(s) using the previously defined individual startup parameters.

At least one of the options `s`, `-host s`, and `-all` must be present.

Server Shutdown

```
down srv [ s | -host h | -all ] [-force] [-kill]
    s                name of the server to be stopped
    -host s          terminate all servers on host h
    -all             terminate all servers
    -force           send SIGTERM immediately, don't wait for
                    transaction end
    -kill            send SIGKILL immediately, don't wait for
                    transaction end
```

This command shuts down the indicated server(s). At least one of the options `s`, `-host s`, and `-all` must be present.

Without `-force` and `-kill`, the server is marked for shut down and will actually be terminated by sending `SIGTERM` after completing the current transaction. With `-force` and `-kill`, the server is terminated instantaneously; this should be handled with extreme caution, as experience shows that relational database systems react differently on such a situation: usually a running transaction is aborted (which is the desired behavior), but sometimes the running transaction is committed (most likely leaving the database in an inconsistent state). See a Unix manual for the difference between `SIGTERM` and `SIGKILL` signals.

The manager on host `h` is not terminated.

4.10 Inter-Manager Status Request

```
check host s
    s      check if slave manager on s is up, retrieve status
           information
```

The master manager can contact a slave manager with this command. Normally this is not necessary as the slave during startup synchronizes with its master. However, if the slave has been launched before the master then the master server this way can manually synchronize with this slave. Similarly, it helps to overcome race conditions during automatic startup in the boot process of a database server network.

4.11 Users and Their Rights

Similarly to operating systems, rasdaman knows named users with access rights associated to them. Each rasdaman client must log in to the system under a specific login name using its specific password; this holds for database clients as well as for database administration. With each login name, a set of rights is associated which determines the set of actions admitted to the user under this login.

To this end, the rasdaman administrator manages user login names (user names) equipped with a password and rights to access the databases.

Attention: There is no way to retrieve a lost password!

The set of known logins as well as the associated rights all are under administrator control; the `define` and `remove` commands serve to add or delete user logins, the `change user` command allows to individually assign rights to a login.

In the rasdaman system's initial state after installation, user `rasadmin` is defined owning all possible rights (see below). A further user `rasquest` is defined which owns read-only access ("R") rights.

For both users, the password initially is identical with the user name. It is highly recommended to change this immediately using the `raspasswd` utility (See Section 5).

Define New User

```
define user u [-passwd p] [-rights r]
    u          login name, must be unique (i.e., not yet existing)
    -passwd p  set login password to pass
               (default: user name)
    -rights r  rights associated with this login
               (default: R, i.e., read-only)
```

The user's password can be changed at any time using the `raspasswd` utility (see Section 5).

Remove User

```
remove user u
```

`u` login name to be removed

The user is removed from the login list and henceforth cannot login to the rasdaman system any more.

User Rights

User rights are indicated by upper case letters. They are divided into two categories: *system rights* and *database rights*. System rights apply to the whole system configuration of a server machine, whereas database rights can be specified individually for a database.

The following system rights are defined:

- C user may change the system configuration
- A access control: the user may perform user management
- S start/stop right: the user may start and stop the system, in particular: rasdaman servers
- I info retrieval: the user may retrieve server status information

The following database rights are defined:

- R user is allowed read data (`select...from...where`) from rasdaman databases
- W user is granted write access (`update, insert, delete`) to rasdaman databases

Notation of Rights

In the `change user` command used for user rights administration, a user's rights set is described by a *rights string*. It is built from letters denoting the rights to be granted.

To revoke a right, leave out the corresponding character. To grant no rights at all, use `-` (minus sign).

No blanks or other characters are allowed in a rights string.

Examples of valid rights strings are:

grant all rights: CASIRW

grant read access only: R

grant no rights at all: -

These are examples for *invalid* rights strings:

Blanks between rights: CA SIR W

Invalid characters I: XYZS
 Invalid characters II: “A_+S

Change User Attributes

`change user u [-name n | -passwd p | -rights r]`

Options:

`u` user login to be updated
`-name n` change user name to `n`
`-passwd p` change password to `p`
`-rights r` change rights of user `u` according to rights string `r`

Change name of user, login password, or user rights.

To change the password it is recommended to use the `raspasswd` utility instead of the `change user` command, as `raspasswd` does not echo the plain password on screen while `rascontrol` does.

Status Information

`list user [-rights]`

`-rights` additionally list rights assigned to each user

List all user names currently defined, optionally with their rights.

4.12 Server Control Options

The following options can be passed to the server when it is started by the server manager using the `up srv` command. Option settings are defined for a particular server using the `rascontrol` command `change srv -xp` which passes the rest of the line after `-xp` on to the server upon starting it (see Section 4.6).

`--log logfile` print log to `logfile`.
 If `logfile` is `stdout`, then log output will be printed to standard output.
 (default: `~rasdaman/log/serverid.log`)

`--mgmtint [m]` server management interval in seconds for garbage collection (default: 120 sec)

`--notimeout` server does not check for client timeouts (default)

`--timeout [t]` client time out in seconds for sign-of-life signal.
 If no `t` indicated: 300 sec; if set to 0, no sign-of-life check is done.
 Activated only if `--mgmtint` is also set.

`--opt n` optimization level
 one of 0, 1, 2, 3, 4 whereby
 0 = no / 4 = maximum optimisation
 (default: 4)

`--transbuffer b`
 set maximum size of transfer buffer to *b* bytes
 (default: 4 MB = 4,194,304 bytes)

4.13 Miscellaneous

Help

`help`

Display top level help page

`help [command]`

`command help`

Display information specific to *command* (both syntax variants are equivalent).

Version Information

`list version`

`version` display rasdaman server version.

Save Changes to Disk

`save`

The `save` operation writes the current configuration and authorization values to disk. All changes done during the session thus become permanent.

rascontrol Termination

`exit`

terminates `rascontrol`.

5 Database User Password Administration

The `raspasswd` utility allows users to interactively change their password. After requesting the user name and the current password, the user is prompted for the new password is twice to exclude typing errors.

If the system configuration consists of several server managers (distributed installation), then the master server manager must be addressed to change the password.

Invocation Synopsis

```
raspasswd [--help] [--host masterhost] [--port p]  
  --help          this help text  
  --host masterhost  
                  master server manager host name  
                  default: localhost  
  --port p      port number of master server manager
```

Example

```
raspasswd localhost  
Login name: mylogin
```

Password: *mypasswd*

New password: *mynewpasswd*

Retype new password: *mynewpasswd*

Note that none of the passwords actually is echoed.

6 Example Database and Programs

6.1 Example Database

A demonstration database is provided as part of the delivery package which contains the collections and images described in the *Query Language Guide*. To populate this database, first install the system as described here in the *Installation Guide* and the base DBMS specific *External Products Integration Guide*, and then invoke `insertdemo.sh` in the `bin` directory. This script makes use of the example images sitting in the `examples` directory, as well as the `insertppm` executable described below.

It is recommended to populate this demo database – it occupies only marginal disk space – first: Successful generation of this database shows overall successful rasdaman installation.

Before the test programs can be used, the demo database has to be created and schema information has to be imported. The following command line creates the database `RASBASE` (see also Section 0):

```
rasdl --basename RASBASE --createdatabase
```

The following imports schema information:

```
rasdl --basename RASBASE
      --read examples/rasdl/basicitypes.dl --insert
```

Finally, the following line establishes the demo database (using a script from the `bin` directory which itself relies on the `insertppm` executable):

```
insertdemo.sh base
```

It is not important whether the `rasdaman` server is running during `rasdl` execution, however, the server is required for the `insertdemo.sh` script, as this is a client application.

For further information on `rasdl` see the *C++ Programming Guide*.

6.2 Example Programs

Several example programs are provided in the `c++` and `java` subdirectories of `$RASDAMAN/share/rasdaman/examples`. Each directory contains a Makefile plus several `.cc` and `.java` sources, resp.

Makefile

The `Makefile` serves to compile and link the sample C++ sources files delivered. It is a good source for hints on the how-tos of compiler and linker flags etc.

insertppm.cc

The `insertppm` program inserts a PPM / PGM / PBM image into a `rasdaman` database. This program serves a dual purpose: On the one hand, it shows how a custom application can be created which inserts single images into a database from a file in some data exchange format. On the other hand, it is the utility to establish the sample database used in the *Query Language Guide*.

A compiled version of this program can also be found in the `bin` directory to avoid that this important utility is overwritten by exploring the sample code.

lookup.cc and lookup.java

The `lookup` program reads a specified collection and prints the MDDs and their content. Any collection from the demo database can be inspected, but be warned of the data volume generated by ASCII printouts.

avg-cell.cc and avg-cell.java

This program computes the average cell value from all images of a given collection.

Note that it requires grayscale images! A good candidate collection is `mr` from the demo database.

avg-cell-red.cc and avg-cell-red.java

Same as `avg-cell`, but takes the red component of an RGB image for averaging.

A good candidate collection is `rgb` from the demo database.

Note

All programs, once compiled and linked, print a usage synopsis when invoked without parameter.

7 Troubleshooting

7.1 Cannot start rasdaman server

Question:

Upon startup of the server, I keep on getting a message

```
Checking if I am the only rasmgr on this
machine....Error: rasmgr instance already active.
```

...however, no rasmgr process is active.

Answer:

A previous forced termination of rasmgr may have left open the portmapper connection. Find it out via

```
rpcinfo -p
```

...and then delete it by issuing, as superuser:

```
rpcinfo -d n 1
```

where *n* is the pertaining address.